



# CROCHET BAG "WINDMILL"



**crochet pattern**

# MATERIALS

- 3 mm polyester cord 400-450 meters
- hook 5mm, yarn needle
- scissors, crochet markers of different colors

In this pattern I use 3 mm polyester cord and a 5 mm crochet hook. My crochet bag has sizes: 16" (41 cm) wide, 12" (31 cm) high.

If you use any other yarn, take a hook 1 sizes smaller than recommended for this yarn (to make the bag more tightly). The size of the bag may vary - it depends on your crochet density and the yarn you choose. The thicker the yarn, the larger the bag.

# ABBREVIATIONS

- ch** - chain
- sc** - single crochet
- inc** - increase ( 2 sc in 1 st)
- sl st** - slip stitch
- dec** - decrease - 2 sc together
- (...)** - amount of stitches after the row






# DESCRIPTION

ch21 (pic 1)

**row 1:** start from the second ch from the hook: 20 sc, ch1, turn **(20)** (pic 2-3)


**row 2:** skip 1 stitch, 18 sc, inc, ch1, turn **(20)** (pic 4-6)

**rows 3 - 60:** skip 1 stitch, 20 sc, ch1, turn **(20)** (pic 7-9) *Take note, the last 20th sc in each rounds must be crocheted a little on the side (pic 7)*



Leave the end of cord of 130"(320 cm) and cut off. Pull out the cord as shown on picture 12.

Crochet second part in the same way



## ANOTHER PART OF THE BAG

Wrap 130"(320 cm) of the cord, fasten it with a thread, as shown on picture 13 and make ch21.

**row 1:** start from the second ch from the hook: 20 sc, ch1, turn **(20)** (pic 2-3)

**row 2:** skip 1 stitch, 18 sc, inc, ch1, turn **(20)** (pic 4-7)

**rows 3 - 55:** skip 1 stitch, 20 sc, ch1, turn **(20)** *Take note, the last 20th sc in each rounds must be crocheted a little on the side*

**row 56:** skip the first stitch: 20 sc, ch50, turn. Try to crochet arm tightly or use a hook of less number (pic 14)

**row 57:** from the second ch from the hook: 48 sc, dec, 20 sc, ch1, turn (pic 15)




**row 58:** skip the first stitch, 68 sc, ch1, turn

**row 59:** skip the first stitch, 47 sc, dec, 19 sc, ch1, turn (pic 16)


**row 60:** skip the first stitch, 67 sc. Leave the end of 40 cm and cut off (pic 17). Pull out the end as shown on picture 18

Crochet second part in the same way

Lay out the parts as shown on picture 20. Long ends of the cord should be in the center. For ease of assembly, place markers as shown on pictures 21



Take part 1 and part 2 (pic 22). Insert hook in the corner of part 2 (pic 23), then on the corner of part 1 (pic 24). Use the end of cord of part 2 and work sl st till the end of part 2 (pic 25-27). Leave the end of 5"(13 cm), cut off. Use yarn needle, move the cord to the wrong side, fasten off and hide it inside stitches (pic 30).



Take part 3 (pic 31). Start from the centre and work sl st joining part 3 and part 2. (pic 32-33)

Join part 4 first with part 3 (pic 34), then with part 1 (pic 35)



Use yarn needle and sew handles as shown on picture 39.  
Fasten off, Hide the end on wrong side.



37



38



39



40



41



42

CONGRATULATIONS  
YOU MADE A WONDERFUL BAG!

